

Remote Visualization

How can I get interactive access to the hpc ressources?

1. Install one-time the NICE DCV Clientsoftware on Your local computer
2. Goto www.tu-ilmenau.de/vis


EnginFrame Version 2020 - Copyright © 1998 - 2021 NICE S.r.L.



A login form with two input fields: 'Username:' and 'Password:'. Below the fields is an orange 'Login' button. The form is centered on a white background.

www.nice-software.com
All trademarks and logos on this page are owned
by NICE s.r.l. or by their respective owners. Legal Notices

3. Login and click at „Desktop Session“



The screenshot shows the NICE DCV web interface. On the left is a sidebar menu with 'Monitor' (containing 'Sessions', 'Hosts', 'Jobs') and 'Services' (containing 'Desktop Session'). The main area is titled 'Sessions' and contains a search bar, a 'Refresh' button, and a table with the message 'No records to view'. On the right is a 'Filters' sidebar with options: 'All', 'Active', 'Starred', and 'Created Today'.

4. Recommendation: Please start Your interactive session through the NICE DCV client software - please set it in the „Settings“ submenu at the tab „NICE DCV (since 2017.0)“:

Menu

Monitor

Sessions

Hosts

Jobs

Services

Desktop Session

Settings

NICE DCV Session Manager (since DCV 2020.2)

NICE DCV (since 2017.0)

VNC / NICE DCV (up to 2016.0)

Viewer Type

Select the type of NICE DCV viewer you want to use to connect to a remote session.

☒ Desktop Client ☐ Browser (open a new browser window)

Display Resolution

Existing sessions will not be affected by changes to this setting.

Specify the display resolution to use for new DCV sessions.

Display Resolution: Custom...

Resolution: 1920 × 1080

Fullscreen Mode: ☒

Use All Monitors: ☐

Cancel

Save

You can Download the latest of the DCV Clientsoftware here: [DCV Client](#)

From:

<https://www1.tu-ilmenau.de/hpcwiki/> - **hpcwiki**

Permanent link:

https://www1.tu-ilmenau.de/hpcwiki/doku.php?id=rem_vis

Last update:

2024/10/22 12:30

