

Remote Visualization

How can I get interactive access to the hpc ressources?

1. Install one-time the NICE DCV Clientsoftware on Your local computer
2. Goto www.tu-ilmeneau.de/vis


EnginFrame Version 2020 - Copyright © 1998 - 2021 NICE S.r.L.



A login form with two input fields: "Username:" and "Password:". Below the fields is an orange "Login" button.

www.nice-software.com
All trademarks and logos on this page are owned
by NICE s.r.l. or by their respective owners. Legal Notices

3. Login and click at „Desktop Session“



The screenshot shows the EnginFrame interface. On the left is a navigation menu with "Monitor" (expanded) containing "Sessions", "Hosts", and "Jobs", and "Services" containing "Desktop Session". The main area is titled "Sessions" and contains a search bar, a "Sort by: Started on" dropdown, and a "Refresh" button. Below these is a table with the message "No records to view". On the right is a "Filters" sidebar with "All", "Active", "Starred", and "Created Today" options.

4. Recommendation: Please start Your interactive session through the NICE DCV client software - please set it in the „Settings“ submenu at the tab „NICE DCV (since 2017.0)“:

Welcome, schwan Settings

Menu ✕

- ▼ Monitor
 - Sessions
 - Hosts
 - Jobs
- ▼ Services
 - Desktop Session

Settings

NICE DCV Session Manager (since DCV 2020.2) | **NICE DCV (since 2017.0)** | VNC / NICE DCV (up to 2016.0)

Viewer Type

Select the type of NICE DCV viewer you want to use to connect to a remote session.

Desktop Client Browser (open a new browser window)

Display Resolution

i Existing sessions will not be affected by changes to this setting.

Specify the display resolution to use for new DCV sessions.

Display Resolution: Custom...

Resolution: 1920 × 1080

Fullscreen Mode:

Use All Monitors:

Cancel Save

From:
<https://www1.tu-ilmenau.de/hpcwiki/> - hpcwiki

Permanent link:
https://www1.tu-ilmenau.de/hpcwiki/doku.php?id=rem_vis&rev=1638193631

Last update: **2021/11/29 14:47**

